

```
In [107]: %config InlineBackend.figure_format='svg'
import numpy
```

```
In [108]: #load the surf module
import surf
#load the surf_data module
import surf_data

#create instances of these classes
dev=surf.Surf()
devData=surf_data.SurfData()
```

```
In [109]: #check the pedestal level
#pedestal in mV = value * 2048 / 4096
dev.vped
```

Out[109]: 4000

```
In [110]: #change the pedestal level
dev.set_vped(1800)
```

```
In [111]: #re-check pedestal level
dev.vped
```

Out[111]: 1800

```
In [112]: #the pedestal variable is set by reading the on-board DAC. You can access that directly like this
dev.i2c.read_dac()
```

```
Reading from MCP4728...
DAC channel A (RFP_VPED_0): register is set to 0x9c4, EEPROM is set to 0x9c4
DAC channel B (RFP_VPED_1): register is set to 0x578, EEPROM is set to 0x578
DAC channel C (RFP_VPED_2): register is set to 0x578, EEPROM is set to 0x578
DAC channel D (VPED)      : register is set to 0x708, EEPROM is set to 0x708
```

Out[112]: 1800

```
In [34]: #re-take pedestal data
devData.pedestalRun()
```


Saving pedestals for board CANOES...

```
Out[34]: array([[1548, 1707, 1540, ..., 1625, 1559, 1623],
               [1555, 1724, 1546, ..., 1653, 1572, 1646],
               [1544, 1725, 1520, ..., 1627, 1571, 1643],
               ...,
               [1550, 1767, 1521, ..., 1639, 1599, 1546],
               [1529, 1757, 1549, ..., 1647, 1573, 1566],
               [1543, 1734, 1535, ..., 1602, 1573, 1467]])
```

```
In [113]: #pedestals are saved to json file: calibrations/surf_calibrations.json
#they are also defined as a class variable:
devData.loadPed()

#histogram the pedestals on CANOES, channel=0
pylab.hist(devData.pedestals[:,0], bins=range(1400, 1700, 10))
pylab.xlabel('Pedestals CH0 [ADC counts]')
```

Out[113]: <matplotlib.text.Text at 0x150ced0c>



```
In [43]: #log some data to check the baseline
#take 50 events and don't save to a file, otherwise make save=True and specify a filename by filename='xxxxxx'
data = devData.log(50, save=False)

#this automatically subtracts the pedestals from the raw data. To not subtract pedestals, specify subtract_ped=False
#this automatically unwraps the data given the trigger position. To not unwrap, specify unwrap=False


logging event...50
```

```
In [49]: #the data is stored in a list of lists
print 'number of events', len(data), ' -- number of channels', len(data[0]), ' -- number of samples per channel per event', len(data[0][0])

number of events 50 -- number of channels 12 -- number of samples per channel per event 1024
```

```
In [114]: #plot event 5 on channel 0
pylab.plot(data[5][0][:], 'o--', color='black', ms=2)
pylab.xlabel('Sample')
pylab.ylabel('Amplitude [ADC counts]')
pylab.ylim([-20,20])
```

Out[114]: (-20, 20)



```


In [115]: #look at the electronics noise on channel 0:
data=numpy.array(data)
pylab.hist(data[:,0,:].flatten(), bins=range(-10, 11, 1), normed=True, color='black', alpha=0.6, label='data')
pylab.xlabel('Noise [ADC counts]')
pylab.ylabel('Normalized entries')

from scipy.stats import norm
mu, std=norm.fit(data[:,0,:].flatten())
x=numpy.linspace(-10, 11, 100)
pdf=norm.pdf(x, mu+0.5, std) #+0.5 to take into account bin edge -> bin center
pylab.plot(x, pdf, '--', color='red', label='fit, \nsigma= {:.2f} mV'.format(std/2)) #just about exactly 2 ADC counts per mV with current configuration

pylab.legend()

```

Out[115]: <matplotlib.legend.Legend at 0x14f834ec>



```

In [83]: #do a pedestal scan, start/stop are pedestal DAC values
#saves to file pedscan.temp (can redefine filename, with filename='xxxxx' argument)

#this takes a few minutes to run
dac_values, lab_values = devData.pedestalScan(start=0, stop=4096, incr=100)

logging event...120

```

```


In [116]: #dac_values = list of values of the pedestal DAC
#lab_values = list of array of pedestal values
print 'size of pedestal scan output array (number of scan points, number of cells per channel, number of channels) =', numpy.array(lab_values).shape

#plot the transfer curve for storage cell 10 on Channel 1:
pylab.plot(dac_values, numpy.array(lab_values)[: ,10,1], label='cell 10, Channel 1')
pylab.xlabel('DAC level')
pylab.ylabel('LAB4D output code [ADC counts]')
pylab.legend(loc='upper left')

```

size of pedestal scan output array (number of scan points, number of cells per channel, number of channels) = (41, 4096, 12)

Out[116]: <matplotlib.legend.Legend at 0x14a5c48c>



```

In [101]: #code exists to generate a linear-interpolated LUT based on the output file from the pedestal scan
#however, it is not yet implemented in the readout or handled to a calibration file...TO DO!

#it can be generated using this:
surf_lut = devData.makeSurfLUT('calibrations/pedscan.temp', pedscan_start=0, pedscan_interval=100)

```

```

In [102]: #this LUT is made by taking the mean response of each channel.
#It does not generate a LUT for each storage cell, which is probably the way to do this in the end
surf_lut.shape


```

Out[102]: (12, 4096)

```
In [117]: #plot the LUT for channel 1:
pylab.plot(surf_lut[1], 'o', ms=2)
pylab.xlabel('LAB4D ADC counts')
pylab.ylabel('milli-volts')

#note: values of -1 indicate the LUT is poorly defined (no mapping)
```

Out[117]: <matplotlib.text.Text at 0x14f8fe4c>



In []: